Operating Systems (Honor Track)

Memory 1: Address Translation and Virtual Memory

Xin Jin Spring 2023

Acknowledgments: Ion Stoica, Berkeley CS 162

Virtualizing Resources



- Physical Reality: Different Processes/Threads share the same hardware
 - Need to multiplex CPU (just finished: scheduling)
 - Need to multiplex use of memory (starting today)
 - Need to multiplex disk and devices (later in term)
- Why worry about memory sharing?
 - The complete working state of a process and/or kernel is defined by its data in memory (and registers)
 - Consequently, cannot just let different threads of control use the same memory
 » Physics: two different pieces of data cannot occupy the same locations in memory
 - Probably don't want different threads to even have access to each other's memory if in different processes (protection)

Recall: Four Fundamental OS Concepts

• Thread: Execution Context

- Fully describes program state
- Program Counter, Registers, Execution Flags, Stack
- Address space (with or w/o translation)
 - Set of memory addresses accessible to program (for read or write)
 - May be distinct from memory space of the physical machine (in which case programs operate in a virtual address space)

• Process: an instance of a running program

- Protected Address Space + One or more Threads
- Dual mode operation / Protection
 - Only the "system" has the ability to access certain resources
 - Combined with translation, isolates programs from each other and the OS from programs

THE BASICS: Address/Address Space



- What is 2¹⁰ bytes (where a byte is abbreviated as "B")?
 - -2^{10} B = 1024B = 1 KB (for memory, 1K = 1024, not 1000)
- How many bits to address each byte of 4KB page?
 - $4KB = 4 \times 1KB = 4 \times 2^{10} = 2^{12} \Longrightarrow 12$ bits
- How much memory can be addressed with 20 bits? 32 bits? 64 bits?
 - Use 2^k

Process Virtual Address Space

- Definition: Set of accessible addresses and the state associated with them
 - $-2^{32} = ~4$ billion **bytes** on a 32-bit machine
- How many 32-bit numbers fit in this address space?
 - 32-bits = 4 bytes, so $2^{32}/4 = 2^{30} = 1$ billion
- What happens when processor reads or writes to an address?
 - Perhaps acts like regular memory
 - Perhaps causes I/O operation
 - » (Memory-mapped I/O)

...

- Causes program to abort (segfault)?
- Communicate with another program



Important Aspects of Memory Multiplexing

- Protection:
 - Prevent access to private memory of other processes
 - » Different pages of memory can be given special behavior (Read Only, Invisible to user programs, etc).
 - » Kernel data protected from User programs
 - » Programs protected from themselves
- Translation:
 - Ability to translate accesses from one address space (virtual) to a different one (physical)
 - When translation exists, processor uses virtual addresses, physical memory uses physical addresses
 - Side effects:
 - » Can be used to avoid overlap
 - » Can be used to give uniform view of memory to programs

• Controlled overlap:

- Separate state of threads should not collide in physical memory. Obviously, unexpected overlap causes chaos!
- Conversely, would like the ability to overlap when desired (for communication)

Alternative View: Interposing on Process Behavior

- OS interposes on process' I/O operations
 - How? All I/O happens via syscalls.
- OS interposes on process' CPU usage
 - How? Interrupt lets OS preempt current thread
- Question: How can the OS interpose on process' memory accesses?
 - Too slow for the OS to interpose *every* memory access
 - Translation: hardware support to accelerate the common case
 - Page fault: uncommon cases trap to the OS to handle

Recall: Uniprogramming

- Uniprogramming (no Translation or Protection)
 - Application always runs at same place in physical memory since only one application at a time
 - Application can access any physical address



 Application given illusion of dedicated machine by giving it reality of a dedicated machine

Primitive Multiprogramming

- Multiprogramming without Translation or Protection
 - Must somehow prevent address overlap between threads



- Use Loader/Linker: Adjust addresses while program loaded into memory (loads, stores, jumps)
 - » Everything adjusted to memory location of program
 - » Translation done by a linker-loader (relocation)
 - » Common in early days (... till Windows 3.x, 95?)
- With this solution, no protection: bugs in any program can cause other programs to crash or even the OS

Multiprogramming with Protection

- Can we protect programs from each other without translation?
 - Yes: Base and Bound!
 - Used by, e.g., Cray-1 supercomputer



Recall: Base and Bound (No Translation)



Recall: General Address translation



- Consequently, two views of memory:
 - View from the CPU (what program sees, virtual memory)
 - View from memory (physical memory)
 - Translation box (Memory Management Unit or MMU) converts between the two views
- Translation ⇒ much easier to implement protection!
 - If task A cannot even gain access to task B's data, no way for A to adversely affect B
- With translation, every program can be linked/loaded into same region of user address space

Recall: Base and Bound (with Translation)



Issues with Simple B&B Method



- Fragmentation problem over time
 - Not every process is same size \Rightarrow memory becomes fragmented over time
- Missing support for sparse address space
 - Would like to have multiple chunks/program (Code, Data, Stack, Heap, etc)
- Hard to do inter-process sharing
 - Want to share code segments when possible
 - Want to share memory between processes
 - Helped by providing multiple segments per process

More Flexible Segmentation



- Logical View: multiple separate segments
 - Typical: Code, Data, Stack
 - Others: memory sharing, etc
- Each segment is given region of contiguous memory
 - Has a base and limit
 - Can reside anywhere in physical memory

Implementation of Multi-Segment Model



- Segment map resides in processor
 - Segment number mapped into base/limit pair
 - Base added to offset to generate physical address
 - Error check catches offset out of range
- As many chunks of physical memory as entries
 - Segment addressed by portion of virtual address
 - However, could be included in instruction instead:
 - » x86 Example: mov [es:bx],ax.
- What is "V/N" (valid / not valid)?
 - Can mark segments as invalid; requires check as well

Access

Error









Observations about Segmentation

- Translation on every instruction fetch, load or store
- Virtual address space has holes
 - Segmentation efficient for sparse address spaces
- When it is OK to address outside valid range?
 - This is how the stack (and heap?) allowed to grow
 - For instance, stack takes fault, system automatically increases size of stack
- Need protection mode in segment table
 - For example, code segment would be read-only
 - Data and stack would be read-write (stores allowed)
- What must be saved/restored on context switch?
 - Segment table stored in CPU, not in memory (small)
 - Might store all of process memory onto disk when switched (called "swapping")

What if not all segments fit in memory?



- Extreme form of Context Switch: Swapping
 - To make room for next process, some or all of the previous process is moved to disk
 - » Likely need to send out complete segments
 - This greatly increases the cost of context-switching
- What might be a desirable alternative?
 - Some way to keep only active portions of a process in memory at any one time
 - Need finer granularity control over physical memory

Group Discussion

- Topic: segmentation
 - What are the problems of segmentation?
- Discuss in groups of two to three students
 - Each group chooses a leader to summarize the discussion
 - In your group discussion, please do not dominate the discussion, and give everyone a chance to speak

Problems with Segmentation

- Must fit variable-sized chunks into physical memory
- May move processes multiple times to fit everything
- Limited options for swapping to disk
- Fragmentation: wasted space
 - External: free gaps between allocated chunks
 - Internal: don't need all memory within allocated chunks

General Address Translation



Paging: Physical Memory in Fixed Size Chunks

- Solution to fragmentation from segments?
 - Allocate physical memory in fixed size chunks ("pages")
 - Every chunk of physical memory is equivalent
 - » Can use simple vector of bits to handle allocation: 00110001110001101 ... 110010
 - » Each bit represents page of physical memory

 $1 \Rightarrow$ allocated, $0 \Rightarrow$ free

- Should pages be as big as our previous segments?
 - No: Can lead to lots of internal fragmentation
 - » Typically have small pages (1K-16K)
 - Consequently: need multiple pages/segment

How to Implement Simple Paging?



- Page Table (One per process)
 - Resides in physical memory
 - Contains physical page and permission for each virtual page (e.g. Valid bits, Read, Write, etc.)
- Virtual address mapping
 - Offset from Virtual address copied to Physical Address
 - » Example: 10 bit offset \Rightarrow 1024-byte pages
 - Virtual page # is all remaining bits
 - » Example for 32-bits: 32-10 = 22 bits, i.e. 4 million entries
 - » Physical page # copied from table into physical address
 - Check Page Table bounds and permissions

Simple Page Table Example



What about Sharing?

Where is page sharing used ?

- The "kernel region" of every process has the same page table entries
 - The process cannot access it at user level
 - But on U->K switch, kernel code can access it AS WELL AS the region for THIS user
- Different processes running same binary!
 - Execute-only, but do not need to duplicate code segments
- User-level system libraries (execute only)
- Shared-memory segments between different processes
 - Can actually share objects directly between processes
 - » Must map page into same place in address space!
 - This is a limited form of the sharing that threads have within a single process

Summary: Paging

Summary: Paging

Summary: Paging

How big do things get?

- 32-bit address space => 2³² bytes (4 GB)
 - Note: "b" = bit, and "B" = byte
 - And *for memory*:
 - » "K" (kilo) = $2^{10} = 1024$
 - » "M"(mega) = 2^{20} = (1024)² = 1,048,576

 $\approx 10^3$ (But not quite!): Sometimes called "Ki" (Kibi)

- pprox 10⁶ (But not quite!): Sometimes called "Mi" (Mibi)
- » "G"(giga) = 2^{30} = (1024)³ = 1,073,741,824 $\approx 10^9$ (But not quite!): Sometimes called "Gi" (Gibi)
- Typical page size: 4 KB
 - how many bits of the address is that ? (remember $2^{10} = 1024$)
 - Ans 4KB = $4 \times 2^{10} = 2^{12} \Rightarrow$ 12 bits of the address
- So how big is the simple page table for *each* process?
 - $2^{32}/2^{12} = 2^{20}$ (that's about a million entries) x 4 bytes each => 4 MB
 - When 32-bit machines got started (vax 11/780, intel 80386), 16 MB was a LOT of memory
- How big is a simple page table on a 64-bit processor (x86_64)?
 - 2⁶⁴/2¹² = 2⁵²(that's 4.5×10¹⁵ or 4.5 exa-entries) x 8 bytes each =
 36×10¹⁵ bytes or 36 exa-bytes!!!! This is a ridiculous amount of memory!
 - This is really a lot of space for only the page table!!!
- The address space is *sparse*, i.e. has holes that are not mapped to physical memory
 - So, most of this space is taken up by page tables mapped to nothing

Group Discussion

- Topic: segmentation vs. paging
 - Can you compare segmentation and paging?
 - What are the pros and cons of each approach?
- Discuss in groups of two to three students
 - Each group chooses a leader to summarize the discussion
 - In your group discussion, please do not dominate the discussion, and give everyone a chance to speak

Page Table Discussion

- What needs to be switched on a context switch?
 Page table pointer and limit
- What provides protection here?
 - Translation (per process) and dual-mode!
 - Can't let process alter its own page table!
- Analysis
 - Pros
 - » Simple memory allocation
 - » Easy to share
 - Con: What if address space is sparse?
 - » E.g., on UNIX, code starts at 0, stack starts at (2³¹-1)
 - » With 4KB pages, need 1 million page table entries!
 - Con: What if table really big?
 - » Not all pages used all the time \Rightarrow would be nice to have working set of page table in memory
- Simple Page table is way too big!
 - Does it all need to be in memory?
 - How about multi-level paging?
 - or combining paging and segmentation

Summary

- Segment Mapping
 - Segment registers within processor
 - Segment ID associated with each access
 - » Often comes from portion of virtual address
 - » Can come from bits in instruction instead (x86)
 - Each segment contains base and limit information
 - » Offset (rest of address) adjusted by adding base
- Page Tables
 - Memory divided into fixed-sized chunks of memory
 - Virtual page number from virtual address mapped through page table to physical page number
 - Offset of virtual address same as physical address
 - Large page tables can be placed into virtual memory
- Next Time: Multi-Level Tables
 - Virtual address mapped to series of tables
 - Permit sparse population of address space